## **Veeam-Agent-03d-Create Recovery Media-Windows**

## Summary

Once you have installed the Veeam agent for Windows it is highly recommended that you create recovery media based on the hardware of the system. You only need one recovery media per hardware configuration. If needed, you can add hardware drivers during the restore process in case the hardware you are restoring to is different.

The recovery media is used to boot the machine into an environment where it can connect to the repository storing your backups and initiate the restore to new hardware, often referred to as a bare metal recovery.

Procedure	Example					
Prerequisites						

- Make sure you have an account with local Administrator permissions.
- Have any additional drivers you want to add to the recovery media readily available.
- Have a storage device with enough free space to hold the recovery media, which typically consumes around 500 MB of space.
   You can create the recovery media to a removable device such as USB or CD. In this guide, we will be saving it as an ISO to be moved to a central location.

## **Create Veeam Recovery Media**

## 1. Open the **Start** menu and open the **Veeam** folder and click **Create Recovery Media**.

Recycle B	lin					
=	Recently ad-	ided	Windows Server			
	Vee:	am Agent for Microsoft Windows				
	File	Level Restore		$\geq$	2	
	📩 Volu	ume Restore	Server Manager	Windows PowerShell	Windows PowerShell ISE	
	Expand $\sim$					
	s		Windows			
	Sear	rch	Administrativ	Task Manager	Control Panel	
	Serv	ver Manager		-	_	
	🔅 Setti	tings	Remote	ø,		
	v		Desktop	Event Viewer	File Explorer	
2.5	New	am `` N				
8	VMv	ware ~				
Ľ	w					
	Win	idows Accessories 🛛 🗸 🗸				
<u> </u>	Win	idows Administrative Tools 🛛 🗸				
\$	Win	Idows Ease of Access V				
Ф	Win	idows PowerShell V				
	р Ц	ernas Secundu				^ 뒤 4 <b>8</b> 930 PM 2/6/2020 ♥

- 2. Select the initial options in the Create Recovery Media wizard and click Next.
  - a. Include decryption key for seamless restore from encrypted backup (protects from password loss)
    - If you configured your backup policy to encrypt your backups, you can specify that password now to avoid having to locate it during a restore.
  - b. Include network connections settings from this computer

     The current network settings will be applied when booting from the media. If you remove the check box, you can
  - specify network settings during the restore process. c. Include the hardware drivers
  - from this computer
    - i. The current drivers on the system will be included on the recovery media, this is helpful when restoring back to the same hardware configuration. Additional drivers can be added during the restore process if needed.
  - d. Include the following additional storage and network hardware drivers
    - You can choose to include drivers for a future restore. This may save time during a restore as you may not have access to the drivers at that time. NOTE:

When you boot your computer from the Veeam Recovery Media, Veeam Agent for Microsoft Windows does not automatically install additional drivers included in the recovery image. You need to install such drivers manually using the Load Driver tool. It is not recommended that you include large amount of additional drivers (1 GB and more) in the Veeam Recovery Media. When you boot your computer from the Veeam Recovery Media, Veeam Agent for Microsoft Windows loads all additional drivers stored in the Veeam Recovery Media into your computer RAM. If the total size of the recovery environment is approximately equal to or greater than the amount of RAM, Windows RE will fail to load.

- On the Image Path step, select the location in which you would like to store the .iso file created and click N ext.
  - a. If you choose a network share, provide credentials with read and write permissions.
- Review your settings and click Create

   Once complete, you should store
   the Recovery Media in a safe
   location so it will be accessible in
   the event of hardware failures.